



INNOVATING SEED RESEARCH

BEYOND THE FIELD

D1 App API

Developer's Manual



INNOVATING SEED RESEARCH



DEVELOPER'S MANUAL

Manual ID Number: #####

Contact Information:

PHONE (515) 382-3506 | WWW.ALMACO.COM

99 M AVENUE NEVADA, IA 50201

Introduction

Read this manual carefully to comprehend all modes of operation and levels of integration for the D1 App. It is vital to your operation and the integrity of your data collection to understand the capabilities and tools the D1 App provides. This manual contains descriptions and specifications of the operation of this software that will enable you to operate and integrate at optimal capacity. This manual contains installation instructions, a troubleshooting guide, and detailed explanations on all pages and modes of integration and operation.

The D1 App is the D1 Connection Software that fully integrates with ALMACO's VantageHD Harvest software and additional software that implements the API functionality. The D1 App has been designed to be a low-maintenance, user-friendly, data collection tool. The software is written to run on any Windows 10 computer and has been optimally designed for the Mobile Demand xTablet 7200.

All specifications, diagrams, and tables in this manual are based on the latest information at printing time. ALMACO reserves the right to make changes at any time without notice. Please contact an ALMACO representative if you have any questions about:

- Material in this manual
- Function and operation of the D1 App
- Integration with the D1 App API
- Troubleshooting, service, or other topics

TO THE PURCHASER:

We at ALMACO wish to extend to each customer our thanks and congratulations for your selection of the D1 App to be included in your agricultural software tool suite for field production.

We believe that our D1 App offers the best performance and value to the D1 harvest hardware. We ensure that the user interface and controls of the software have been specially designed for your ease of use. The data captured through this software has been tested to ensure optimal results for your precision research operation.

Our skilled workforce has engineered the ALMACO D1 App software at our USA headquarters to meet your performance, quality, and reliability expectations.

You and your company have joined the ever-growing group of agricultural researchers using ALMACO products. The ALMACO family is thankful for the opportunity to earn your business and we will continue to strive to meet your after-sale service needs with our 24/7/365 customer support.

Please read the information contained within the operator's manual carefully before operating **your** software.

Respectfully,

A handwritten signature in blue ink, appearing to read 'Patrick Clem', with a stylized flourish at the end.

Patrick Clem, CEO

Contents

1	SAFETY	5
<hr/>		
1.1	General Safety	5
2	INTEGRATION	8
<hr/>		
2.1	Programming Conventions	8
2.2	How to Use Our MQTT API	8
2.3	How to Establish a Connection	9
2.4	Subscribing to Topics	11
2.5	Publishing To Topics	12
2.6	D1 App Topics	13
2.7	Helpful Libraries and Tools	19
3	TROUBLESHOOTING	20
<hr/>		
3.1	General Troubleshooting	Error! Bookmark not defined.
3.2	Troubleshooting chart	Error! Bookmark not defined.
4	ADDITIONAL RESOURCES	20
<hr/>		
4.1	Warranty	20
<hr/>		

5 SAFETY

5.1 General Safety

Every year, many accidents occur which could have been avoided with a few seconds of thought and a safer approach to handling agricultural machinery and implements.

Designers build in as many safety features as possible, such as safety shields for belts, chains, sprockets, etc., but the designer cannot guarantee safety.

It is an end user's responsibility to ensure no hazards are occurred by operators.

Do not place fingers into open moving parts; injury may occur.

Do not climb, sit, or stand on the equipment.

Do not allow foreign objects into the equipment.

Do not use equipment in an unintended manner.

Do not use it in potentially explosive atmospheres.

These general safety precautions and the safety decals on the machine are intended to help avoid accidents and create a safe working environment.

5.1.1.1 Personal Protective Equipment

The following Personal Protective Equipment is to be worn while working around the D1 Unit:

Proper PPE for normal operation

- Safety glasses

Proper PPE to be worn during service to D1 Unit

- Safety glasses

5.1.1.2 Recognize Safety Information

This is the safety alert symbol. When you see this symbol on your machine or in this manual, be alert to the potential for personal injury.

Follow recommended precautions and safe operating practices.



5.1.1.3 Follow Safety Instructions

Carefully read all safety messages in this manual and the safety decals on your machine. Keep all decals in good condition and replace any that are missing or damaged. New decals are available from ALMACO. Refer to **Safety Decal Locations** later in this section for ordering information. Be sure new equipment, components, and repair parts display all required safety decals.



5.1.1.4 Service Safety

Disconnect D1 before performing any electrical work or service on the machine.

5.1.1.5 Handle Chemical Products Safely

Direct exposure to hazardous chemicals can cause serious injury.

A Safety Data Sheet (SDS) provides specific details on chemical products: physical and health hazards, safety procedures, and emergency response techniques.

Check the SDS before you start any job using hazardous chemicals, so you will know the risks and how to handle chemicals safely. Follow the procedures and use the recommended equipment.

5.1.1.6 Observe Environmental Protection Regulations

Before disposing of chemically treated seed, know the correct method of disposal. Observe relevant environmental protection regulations when disposing of seeds and cartridges.

6 INTEGRATION


6.1 Programming Conventions

This manual has been written for developers to enable them to connect to our software and build onto our technology. Our API (Application Programming Interface) enables the consistent transfer of data from our system to yours. Our MQTT API implements the standard MQTT architectural pattern and protocol of clients publishing and subscribing to predetermined topics.

MQTT stands for Message Queuing Telemetry Transport and is a lightweight publish-subscribe messaging protocol. In standard MQTT architecture, there is one MQTT broker with a set of topics. Clients are external components communicating with the broker. A client can publish data to topics and subscribe to receive data from topics. Once a client is subscribed to a topic, the broker will ensure that the client will receive all published content on that topic.

6.2 How to Use Our MQTT API

The D1 Application uses an MQTT broker architecture to transfer information via JSON messages. Within the D1 App, there are 5 topics that an integrating software can publish and subscribe to.



6.3 How to Establish a Connection

As with all coding solutions, there are many clever methods to how this can be done but the following is one solution for connection done in C#. For additional solutions in other coding languages, there is much documentation online on MQTT connections. We recommend you take the information on the topics, information structure, and coding logic flow and write your code based on MQTTs language-specific documentation.

Connection with any MQTT broker starts through setting up a client and subscribing to the necessary topics.

```
private IManagedMqttClient managedMqttClient = new MqttFactory().CreateManagedMqttClient();
```

```
var tlsOptions = new MqttClientTlsOptions  
{  
    UseTls = false,  
    IgnoreCertificateChainErrors = true,  
    IgnoreCertificateRevocationErrors = true,  
    AllowUntrustedCertificates = true  
};
```

MQTT requires that there are configurations for MQTT TLS (Transport Layer Security). Our system does not require TLS as it is an internal communication on localhost. More important configurations for your implementation of our API are below. Your ClientId can be a string of your choice but ensure that you select port 1883, server of localhost, and that the rest of the options are configured correctly. The details of the configurations are essential for connection.

```
var options = new MqttClientOptions  
{  
    CleanSession = true,  
    ClientId = "HarvestClient",  
    KeepAlivePeriod = TimeSpan.FromSeconds(5),  
    ProtocolVersion = MqttProtocolVersion.V500,  
    ChannelOptions = new MqttClientTcpOptions  
    {  
        Server = "localhost",  
        Port = 1883,  
        TlsOptions = tlsOptions  
    }  
};
```

```
await managedMqttClient.StartAsync(
    new ManagedMqttClientOptions
    {
        ClientOptions = options
    });
```

6.4 Subscribing to Topics

Once you have identified what topics you would like to subscribe to, you must internally code the subscribing connection.

```
await managedMqttClient.SubscribeAsync("d1-readings", MqttQualityOfServiceLevel.AtLeastOnce);
```

After you have set up the connection and you have subscribed to the correct topics, it is necessary to handle the MQTT-received messages. Depending on the topic received, you can implement functionality accordingly.

```
/// <summary>
/// Handles the received application message using the specified event args.
/// </summary>
/// <param name="eventArgs">Event arguments passed into the method.</param>
/// <returns></returns>
public Task HandleReceivedApplicationMessage(MqttApplicationMessageReceivedEventArgs eventArgs)
{
    var thisTopic = eventArgs.ApplicationMessage?.Topic;
    var thisPayload = eventArgs.ApplicationMessage.ConvertPayloadToString();

    var errors = new List<string>();

    try
    {
        switch (thisTopic)
        {
```

6.5 Publishing To Topics

To publish to any topic, one must create a JSON object, serialize the object, and publish it to the desired topic.

```
JSON_Response thisResponse = new JSON_Response
{
    timestamp = DateTime.Now,
    command_string = command,
    response_string = response
};
```

```
var output = JsonConvert.SerializeObject(thisResponse, Formatting.Indented);
```


```
MqttPublish("d1-command", output);
```

Depending on the topic, the input, and output will look different. All will be serialized JSON objects with a time stamp, but the format of each topic is specific to the data being transferred. Continue to the topics section to see the format information.

6.6 D1 App Topics

D1 Readings

The 'd1-readings' topic is where the D1 App publishes all data information pertaining to weight, test weight, moisture, and temperature. These messages will be posted frequently while D1 App is connected to a D1 Unit.



The format of the 'd1-readings' JSON is:


```
{
  "timestamp": "2023-05-04T10:00:58.9234876-05:00",
  "left_weight": 10.114106178283691,
  "left_test_weight": "NaN",
  "left_moisture": "NaN",
  "left_temperature": "NaN",
  "right_weight": "NaN",
  "right_test_weight": 10.114106178283691,
  "right_moisture": 10.114106178283691,
  "right_temperature": 10.114106178283691,
  "left_weight_raw": 10.114106178283691,
  "left_test_weight_raw": 10.114106178283691,
  "left_moisture_raw": 10.114106178283691,
  "left_temperature_raw": 10.114106178283691,
  "right_weight_raw": 10.114106178283691,
  "right_test_weight_raw": 10.114106178283691,
  "right_moisture_raw": 10.114106178283691,
  "right_temperature_raw": 10.114106178283691
}
```

The values on the right side will vary based on the configurations of the machine, the implemented calibration curve, and the date-time. If the combine is not a dual plot machine, it will not have both left and right values. If the machine is not giving a value for a parameter, the JSON will contain a "NaN" as a place holder. The first 8 values of the JSON (not the timestamp) are the raw uncalibrated voltages relating to the left-hand value. The next 8 are the fully calibrated value based on the current calibration curve implemented in the D1 App Calibration tab.

Within the code, we recommend creating a readings object and serializing and deserializing the object using the System.Text.Json namespace in .NET.

D1 Command

The 'd1-commands' topic is where the D1 App subscribes to all commands that can be published by external components of software. There are 2 commands an external software can publish to the 'd1-commands' topic with positive result, these being "hide" and "show".



The format of the 'd1-commands' JSON is:


```
{  
  "timestamp": "2023-05-04T10:00:38.987654-5:00",  
  "command_string": "show"  
}
```

```
{  
  "timestamp": "2023-05-04T10:00:38.987654-5:00",  
  "command_string": "hide"  
}
```


The command to hide will minimize the D1 App to the service tray of the windows device that the D1 App is running on. The command to show the D1 App will bring the App the foreground of the windows machine.

D1 Response

The 'd1-response' topic is the location of connection updates. The D1 App will post to the 'd1-response' updates the command of connected and the response of true or false. If the Connection was a success, then the response is true. If the D1 App failed to connect to the D1 unit, then the response is false.




The format of the 'd1-response' JSON is:

```
{
  "timestamp": "2023-05-04T10:00:38.987654-5:00",
  "command_string": "Connected",
  "response_string": "true"
}
```

SS Commands

To create a backwards compatibility with harvest software that previously interfaced with the Seed Spector LRX, the D1 App supports the 'ss-command' and 'ss-response' topics. The D1 App will emulate the SS in that it will accept the exact same command strings and respond with a Seed Spector result.



An example of a 'ss-command' JSON is:

```
{
  "timestamp": "2023-05-02T10:13:17.5846009-05:00",
  "command_string": "$Z14W020Z6"
}
```

The D1 App will process the command string as if it was an SS LRX and respond with publishing to the 'ss-response' with both the command and the response to the command.

An example of a 'ss-response' JSON is:

```
{  
  "timestamp": "2023-05-02T10:13:13.8266056-05:00",  
  "command_string": "R012345",  
  "response_string": "17.57\r\n9.92\r\n13.94\r\n16.24\r\n9.83\r\n9.72"  
}
```

In this example the command string is: R012345. The value R is the request for the calibrated readings and the numbers refer to which readings are requested. In this case:

0: left_moisture = 17.75

1: left_weight = 9.92

2: right_weight = 13.94

3: right_moisture = 16.24

4: left_temperature = 9.83

5: right_temperature = 9.72

To know more about the command strings and responses, refer to the LRX manual.

6.7 Helpful Libraries and Tools

Libraries that we use to perform the MQTT operations:

- MQTTnet version 4.1.3.436
- MQTTnet.Extensions.ManagedClient 4.1.3.436

<https://github.com/dotnet/MQTTnet>

A helpful tool for working with MQTT that we recommend is MQTT Explorer.

<https://apps.microsoft.com/store/detail/mqttexplorer/9PP8SFM082WD?hl=en-us&gl=us>

7 TROUBLESHOOTING

8 ADDITIONAL RESOURCES

8.1 Warranty

ALMACO End User License Agreement ("EULA")

Grant of Software License

This license is being granted by ALMACO, a company incorporated in the state of Iowa, U.S.A.

ALMACO grants to you (the "Licensee") a non-exclusive right to use this ALMACO software including any updates thereto provided to you by ALMACO (the "Software").

This license agreement is valid without the Licensor's or Licensee's signatures. It becomes valid upon the Licensee's use of the Software.

Ownership of Software. ALMACO or its licensors may have patents or pending patent applications, trademarks, copyrights, trade secret rights, or intellectual property rights covering the Software and all materials delivered to you along with the Software (user manuals and other documentation). You acknowledge that the Software and such materials are the property of ALMACO or its licensors and that the only rights you have with respect to the Software and related materials is the right to use them in accordance with the terms of this license. You acknowledge that no title to the intellectual property in the Software is transferred to you. You may not sublicense the use or ownership of this software to any other parties.

Additional Software, Services, and Updates. This EULA applies to updates, supplements, add-on components, and product support services of the Software that

you may obtain from ALMACO or its affiliates, providers, or licensors, unless you accept updated terms or another agreement governs.

Modification and Reverse Engineering. You agree that you will not and will not attempt to, (a) modify any part of the Software or (b) reverse engineer, decompile, translate, or disassemble any part of the Software.

Separation of Components. The Software is licensed as a single product. Its component parts may not be separated for use on more than one system. You may only use this software with the product it was intended to operate.

Backup Copy. You may make one (1) backup copy of the Software. You may use this backup copy solely for your archival purposes and to reinstall the Software on its affiliated system. You may not loan, rent, lend, or otherwise transfer the backup copy to another user.

Limited Warranty. ALMACO warrants to the original consumer purchaser of this Software that the recording media on which the software is recorded will be free from defects in material and workmanship for one year from date of purchase. If the medium is found defective ALMACO agrees to replace, free of charge, any products discovered to be defective upon receipt of the defective product

No Liability for Consequential Damages. Except as prohibited by law, neither ALMACO nor its affiliates, providers, or licensors are liable to you for any consequential, special, indirect, or incidental damages whatsoever (including, without limitation, damages for loss of data or computer time, loss of business profits, business interruption, loss of business information, or any other pecuniary loss) arising out of the delivery, use, or inability to use the Software. This limitation shall apply even if any component of the Software fails of its essential purpose. In no event shall ALMACO or its affiliates, providers, or licensors be liable for any amount in excess of the license or other fees paid by you to ALMACO, if any.

Notice Regarding Data Security. To help protect against data loss and breaches of security, frequently and periodically back up your data and system information.

Consent of Data Use. You agree that ALMACO may collect and use technical information gathered in any manner as part of product support services related to the Software. ALMACO may use this information solely to improve their products or provide

customized services or technologies to you. ALMACO may disclose this information to others, but not in a form that may personally identify you.

Exclusivity of Use and Transfer. The Software may not be shared, transferred to, or used concurrently on multiple computers. The Software is licensed as part of an integrated system and may only be used with the affiliated system. You may transfer your rights under this EULA only as part of a permanent sale or transfer of the complete system, provided you retain no copies of the Software. If the Software is an upgrade, any transfer must also include all prior versions of the Software. The transfer may not be an indirect transfer, such as a consignment. Prior to the transfer, the end user receiving the Software must agree to all of the terms in this EULA.

Product Support. For product support, please refer to the ALMACO support number provided in the documentation of the Software or integrated system. ALMACO reserves the right, at any time, to discontinue service, product support, and the issuance of updates for the Software.

Export Restrictions. You acknowledge that the Software is subject to U.S. and European Union export jurisdiction. You agree to comply with all applicable national and international laws that apply to the Software, including U.S. Export Administration Regulations, end-user, end-use, and destination restrictions issued by the U.S. and other governments.

Severability. In the event that any provision of this agreement is found to be illegal by any court of jurisdiction. All remaining provision will survive and continue to be in full effect.

Jurisdiction. The validity, interpretation and performance of this Agreement shall be controlled by and construed under the laws of the State of Iowa. End User agrees that all actions, litigation or proceedings related to this agreement in state or federal court will be conducted in the State of Iowa, the end user waives any objection to this jurisdiction.

Termination. You may terminate this license at any time by destroying the Software and all copies. Without prejudice to any other rights, and without notice, ALMACO may terminate this EULA if you fail to comply with the terms and conditions of this license. In such an event, you must destroy all copies of the Software and all its component parts.



Scan Here
To Contact
Service